


## Lecture 6: Water in Atmosphere



- Indices of Water Vapor Content
- Adiabatic Process
- Lapse Rate and Stability




## Introduction

- Over 70% of the planet is covered by water
- Water is unique in that it can simultaneously exist in all three states (solid, liquid, gas) at the same temperature
- Water is able to shift between states very easily
- Important to global energy and water cycles



## How Much Water Vapor Is Evaporated Into the Atmosphere Each Year?

- On average, 1 meter of water is evaporated from oceans to the atmosphere each year.
- The global averaged precipitation is also about 1 meter per year.




## How Much Heat Is Brought Upward By Water Vapor?

- Earth's surface lost heat to the atmosphere when water is evaporated from oceans to the atmosphere.
- The evaporation of the 1m of water causes Earth's surface to lost 83 watts per square meter, almost half of the sunlight that reaches the surface.
- Without the evaporation process, the global surface temperature would be 67°C instead of the actual 15°C.



## Phase Changes of Water




(from *Meteorology: Understanding the Atmosphere*)

- Latent heat is the heat released or absorbed per unit mass when water changes phase.
- Latent heating is an efficient way of transferring energy globally and is an important energy source for Earth's weather and climate.



## Water Vapor In the Air



(from *Understanding Weather & Climate*)

- Evaporation:** the process whereby molecules break free of the liquid volume.
- Condensation:** water vapor molecules randomly collide with the water surface and bond with adjacent molecules.



## Indices of Water Vapor Content

- by mass

$$\text{Mixing ratio} = \frac{\text{mass of water vapor}}{\text{mass of dry air}}$$

$$\text{Specific humidity} = \frac{\text{mass of water vapor}}{\text{total mass of air}}$$

$$\text{Absolute humidity} = \frac{\text{mass of water vapor}}{\text{volume of air}}$$

- by vapor pressure


$$\text{RH} = \frac{\text{actual vapor pressure}}{\text{saturation vapor pressure}} \times 100 \text{ percent.}$$

$$\text{RH} = \frac{\text{actual mixing ratio}}{\text{saturation mixing ratio}} \times 100 \text{ percent.}$$

- by temperature → Dew Point Temperature




## Specific vs. Relative Humidity



- Specific Humidity:** How many grams of water vapor in one kilogram of air (in unit of gm/kg).
- Relative Humidity:** The percentage of current moisture content to the saturated moisture amount (in unit of %).
- Clouds form when the relative humidity reaches 100%.




## Observed Specific Humidity



(from *Meteorology Today*)



## Vapor Pressure




(from *Meteorology Today*)

- ❑ The air's content of moisture can be measured by the pressure exerted by the water vapor in the air.
- ❑ The total pressure inside an air parcel is equal to the sum of pressures of the individual gases.
- ❑ In the left figure, the total pressure of the air parcel is equal to sum of vapor pressure plus the pressures exerted by Nitrogen and Oxygen.
- ❑ High vapor pressure indicates large numbers of water vapor molecules.
- ❑ Unit of vapor pressure is usually in mb.



## Saturation Vapor Pressure



- ❑ Saturation vapor pressure describes how much water vapor is needed to make the air saturated at any given temperature.

- ❑ Saturation vapor pressure depends primarily on the air temperature in the following way:

$$\frac{de_s}{dT} = \frac{L}{T(\alpha_v - \alpha_l)} \quad \text{The Clausius-Clapeyron Equation}$$


$$\rightarrow e_s \cong 6.11 \cdot \exp\left\{\frac{L}{R_v} \left(\frac{1}{273} - \frac{1}{T}\right)\right\}$$

- ❑ Saturation pressure increases exponentially with air temperature.

L: latent heat of evaporation;  $\alpha$ : specific volume of vapor and liquid



## How to Saturate the Air?



(from "IS The Temperature Rising")

- ❑ Three ways:
  - (1) Increase (inject more) water vapor to the air (A  $\rightarrow$  B).
  - (2) Reduce the temperature of the air (A  $\rightarrow$  C).
  - (3) Mix cold air with warm, moist air.




## “Runway” Greenhouse Effect

- ❑ If a planet has a very high temperature that the air can never reach a saturation point
- ➔ Water vapor can be added into the atmosphere.
- ➔ More water vapor traps more heat (a greenhouse effect)
- ➔ The planet’s temperature increases furthermore
- ➔ Ever more water evaporated into the atmosphere
- ➔ More greenhouse effect
- ➔ More warming
- ➔ More water vapor
- ➔ .....



## Dew Point Temperature




(from *The Atmosphere*)

- ❑ Dew point temperature is another measurement of air moisture.
- ❑ Dew point temperature is defined as the temperature to which moist air must be cooled to become saturated without changing the pressure.
- ❑ The closer the dew point temperature is to the air temperature, the closer the air is to saturation.
- ❑ Dew points can be only equal or less than air temperatures.



## Frost Point Temperature

- ❑ When air reaches saturation at temperatures below freezing the term *frost point* is used.




## Measuring Humidity

- ❑ The easiest way to measure humidity is through use of a *sling psychrometer* - A pair of thermometers one of which has a wetted cotton wick attached to the bulb.
- ❑ The two thermometers measure the wet and dry bulb temperature.
- ❑ Swinging the psychrometer causes air to circulate about the bulbs.
- ❑ When air is unsaturated, evaporation occurs from the wet bulb which cools the bulb.
- ❑ Once evaporation occurs, the wet bulb temperature stabilizes allowing for comparison with the dry bulb temperature.
- ❑ The wet bulb depression is found with a greater depression indicative of a dry atmosphere.
- ❑ Charts gauge the amount of atmospheric humidity.
- ❑ *Aspirated* and *hair hygrometers* are alternatives.



## Dew



- ❑ Liquid condensation on surface objects.
- ❑ Diabatic cooling of surface air typically takes place through terrestrial radiation loss on calm, cool, clear nights.

(a)



## Frost




- ❑ Similar to dew except that it forms when surface temperatures are below freezing.
- ❑ Deposition occurs instead of condensation.

(b)



## Fog



- Simply a surface cloud
- Fog formed when air either (1) cools to the dew point,
- (2) has moisture added, or
- (3) when cooler air is mixed with warmer moister air.



## Different types of fog found throughout the U.S.



## Diabatic Process

- ❑ Involve the direct addition or removal of heat energy.
- ❑ Example: Air passing over a cool surface loses energy through conduction.




## Adiabatic Process

- ❑ If a material changes its state (pressure, volume, or temperature) without any heat being added to it or withdrawn from it, the change is said to be adiabatic.
- ❑ The adiabatic process often occurs when air rises or descends and is an important process in the atmosphere.



## Air Parcel Expands As It Rises...



(from *The Blue Planet*)

- ❑ Air pressure decreases with elevation.
- ❑ If a helium balloon 1 m in diameter is released at sea level, it expands as it floats upward because of the pressure decrease. The balloon would be 6.7 m in diameter as a height of 40 km.




## What Happens to the Temperature?

- ❑ Air molecules in the parcel (or the balloon) have to use their kinetic energy to expand the parcel/balloon.
- ❑ Therefore, the molecules lost energy and slow down their motions
  - ➔ The temperature of the air parcel (or balloon) decreases with elevation. The lost energy is used to increase the potential energy of air molecular.
- ❑ Similarly when the air parcel descends, the potential energy of air molecular is converted back to kinetic energy.
  - ➔ Air temperature rises.




## Dry Adiabatic Lapse Rate



(from *Meteorology: Understanding the Atmosphere*)



## Moist Adiabatic Lapse Rate



(from *Meteorology: Understanding the Atmosphere*)




## Dry and Moist Adiabatic Lapse Rates

- ❑ Dry adiabatic lapse rate is constant =  $10^{\circ}\text{C}/\text{km}$ .
  - ❑ Moist adiabatic lapse rate is NOT a constant. It depends on the temperature of saturated air parcel.
  - ❑ The higher the air temperature, the smaller the moist adiabatic lapse rate.
- ➔ When warm, saturated air cools, it causes more condensation (and more latent heat release) than for cold, saturated air.




## Concept of Stability



(from *Meteorology Today*)



## Static Stability



- ❑ Static stability is referred to as air's susceptibility to uplift.
- ❑ The static stability of the atmosphere is related to the vertical structure of atmospheric temperature.
- ❑ To determine the static stability, we need to compare the lapse rate of the atmosphere (environmental lapse rate) and the dry (moist) adiabatic lapse rate of a dry (moist) air parcel.



ESS55  
Prof. Jin-Yi Yu


## Environmental Lapse Rate

- ❑ The environmental lapse rate is referred to as the rate at which the air temperature surrounding us would be changed if we were to climb upward into the atmosphere.
- ❑ This rate varies from time to time and from place to place.



ESS55  
Prof. Jin-Yi Yu

## Static Stability of the Atmosphere




$\Gamma_e$  = environmental lapse rate  
 $\Gamma_d$  = dry adiabatic lapse rate  
 $\Gamma_m$  = moist adiabatic lapse rate

- ❑ Absolutely Stable  
 $\Gamma_e < \Gamma_m$
- ❑ Absolutely Unstable  
 $\Gamma_e > \Gamma_d$
- ❑ Conditionally Unstable  
 $\Gamma_m < \Gamma_e < \Gamma_d$



ESS55  
Prof. Jin-Yi Yu

## Absolutely Stable Atmosphere




(from *Meteorology Today*)



ESS55  
Prof. Jin-Yi Yu




## Absolutely Unstable Atmosphere



(from *Meteorology Today*)

ESSS5  
Prof. Jin-Yi Yu


## Conditionally Unstable Atmosphere



(from *Meteorology Today*)

ESSS5  
Prof. Jin-Yi Yu

## Day/Night Changes of Air Temperature




(from *Is the Temperature Rising?*)

- ❑ At the end of a sunny day, warm air near the surface, cold air aloft.
- ❑ In the early morning, cold air near the surface, warm air aloft.
- ❑ The later condition is called "inversion", which inhibits convection and can cause severe pollution in the morning.

ESSS5  
Prof. Jin-Yi Yu

## Stability and Air Pollution



Neutral Atmosphere (Coning)

Stable Atmosphere (Fanning)

Unstable Atmosphere (Looping)

Stable Aloft; Unstable Below (Fumigation)

Unstable Aloft; Stable Below (Lofting)

(from *Is the Temperature Rising?*)

ESSS5  
Prof. Jin-Yi Yu

## Potential Temperature ( $\theta$ )

- The potential temperature of an air parcel is defined as the temperature the parcel would have if it were moved adiabatically from its existing pressure and temperature to a standard pressure  $P_0$  (generally taken as 1000mb).

$$\theta = T \left( \frac{P_0}{P} \right)^{\frac{R}{C_p}}$$

$\theta$  = potential temperature  
 $T$  = original temperature  
 $P$  = original pressure  
 $P_0$  = standard pressure = 1000 mb  
 $R$  = gas constant =  $R_d = 287 \text{ J deg}^{-1} \text{ kg}^{-1}$   
 $C_p$  = specific heat =  $1004 \text{ J deg}^{-1} \text{ kg}^{-1}$   
 $R/C_p = 0.286$




## Importance of Potential Temperature


- In the atmosphere, air parcel often moves around adiabatically. Therefore, its potential temperature remains constant throughout the whole process.
- Potential temperature is a conservative quantity for adiabatic process in the atmosphere.
- Potential temperature is an extremely useful parameter in atmospheric thermodynamics.



## Adiabatic Chart





(from *Atmospheric Sciences: An Intro. Survey*)




(from *The Physics of the Atmospheres*)


The expression of potential temperature can be modified into:  
 $T = (\text{constant} * \theta) P^{0.286}$



(from *Meteorology Today*)




## Adiabatic Chart: $P$ and $T$



(from *Meteorology Today*)




## Adiabatic Chart: *Dry Adiabatic* / $\theta$




(from *Meteorology Today*)




## Adiabatic Chart: *Moist Adiabatic*



(from *Meteorology Today*)




## Adiabatic Chart: *Mixing Ratio*



(from *Meteorology Today*)




## An Example



ESSS5  
Prof. Jin-Yi Yu

## Applications of Adiabatic Chart



ESSS5  
Prof. Jin-Yi Yu